
Customizing ArchiMate language


The [ArchiMate](#) language can be customized for domain-specific purposes. You can add additional attributes to and define specialization of ArchiMate elements and relationships. We will show you how to do this in this article.

Adding attributes to ArchiMate elements and relationships


The ArchiMate language contains only the elements and relationships that are necessary for general architecture modeling. If, for example, you need to perform model-based performance or cost estimation, or to attach additional information to model elements and relationships, you need to customize the language by adding additional attributes.

The steps below shows you how to add additional attributes to Application Component. The same technique can be applied on other model element types.


1. Select **Window > Configuration > Configure Default Tagged Values...** from the application toolbar. This shows the **Configure Default Tagged Values** window.




2. On the left hand side, find and select the type of ArchiMate element/relationship to add attributes to, in this case, Application Component.



3. On the right hand side, click **Add**, and then select the type of attribute to add. This adds a new attribute.




4. Enter the name of attribute and press **Enter** to confirm.





Adding the attribute Fixed Cost

5. Repeatedly add the other attributes.



6. Click **OK** to confirm.

7. The instance of modified ArchiMate element/relationship will have custom attributes attached as tagged values. You can inspect and enter the values in the specification window.




Specialization of elements and Relationships

To specialize elements and relationships are to define new elements or relationships based on the existing ones. Specialized ArchiMate elements inherit the properties of their generalized form. A specialized elements resemble a stereotype as it is used in UML. In other words, a specialized element can be denoted with the stereotype notation, which consists of a pair of angled brackets surrounding the name of stereotype. Finally, for a specialized concept, certain attributes may be predefined as tagged values.


Defining specialized element

Follow the steps below to define specialized elements readily by used in your model.


1. Select **Window > Configuration > Manage Stereotypes...** from the application toolbar. This shows the **Manage Stereotypes** window.




2. On the left hand side, select the kind of ArchiMate element or relationship that you want to specialize.



3. On the right, click **Add...** to create a stereotype.



4. Enter the name and the description of the stereotype. If you like you may provide an icon as well. Element instances can be optionally presented as the icon. Besides, you may attach custom attributes to the stereotype under the **Tagged Value Definitions** tab.




5. Click **OK** to confirm and return to the **Manage Stereotype** window.
6. Click **OK** again to confirm and close the **Manage Stereotype** window.


Specializing an element

Follow the steps below to set an existing ArchiMate element to be in specialized form.

1. Right click on the element that you want to set it to be in specialized form. Select **Stereotypes > %STEREOTYPE%** from the popup menu.




The stereotype is added to the top of the shape.




Customizing the diagram toolbar for easy creation of specialized element

By default, diagram toolbar lists only the generalized elements. To facilitate modeling with specialized elements, you can customize the diagram toolbar to list also the specialized elements.


1. Right click on the diagram toolbar in the ArchiMate diagram and select **Configure Buttons...** from the popup menu. This shows the **Configure Buttons** window.




2. Select the stereotype on the left and the click > to add it to pane on the right.



3. Click **OK**.
4. You can now create the specialized ArchiMate element via the diagram toolbar. Select it.




5. Click on the diagram to create a specialized element. Enter the name and press **Enter** to confirm




Customized symbol

To present a specialized ArchiMate shape with customized symbol, follow the steps below.

Firstly, make sure you have provided an icon in defining stereotype, like this:



To make a specialized element show as that icon image, right click on the specialized element and select **Presentation Options > Stereotype Icon** from the popup menu.




The element is presented as the icon image.



Using ArchiMate's examples of specialization

Visual Paradigm provide predefined specializations of the ArchiMate concepts and relationships according to Chapter 15 (Language Customization Mechanisms) of the ArchiMate 3.0 Specification. To use it, right click on an ArchiMate element and select **Stereotypes > %STEREOTYPE%** from the popup menu.



The figure below shows the result.

